



TELEX

Radio Dispatch

Radio Dispatch Engineering Group

C-Soft BETA Version 7.601 Engineering Release Notes

Notice:

The content in this document represents the current view of Bosch Security Systems as of the date of publication. Because Bosch Security Systems responds continually to changing market conditions, this document should not be interpreted as a commitment on the part of Bosch Security Systems. Bosch Security Systems cannot guarantee the accuracy of any information presented after the date of publication.

Bosch Security Systems, Inc. All rights reserved

Revision A

March 17, 2020

Table of Contents

1. Revision History	1
2. Overview	1
3. New Features	1
Version 7.601	1
4. Improved Features and Fixed Issues	1
Version 7.601	1
5. Known Issues	1
Version 7.601	1
6. Compatibility	1
Version 7. 563	1
7. Installation and Upgrade	1
Version 7.563	1

1. Revision History

Revision	Date	Author	Description
A	03/17/2020	Radio Dispatch Engineering Group	Updated to C-Soft Version 7.601

2. Overview

This is the release notes for C-Soft BETA Version 7. firmware/software. This release contains new features, improved features, and fixed issues.

IMPORTANT: Beta version software products are NOT SUPPORTED. Beta version software products are software products that are still under DEVELOPMENT and TESTING. If you download a beta version software product then you are getting an exclusive look at a new software product and you are also acting as a beta test team member therefore any bugs, problems or suggested improvements should be reported to engineering or product management. Customer is advised to backup important data and to not use the beta software products in a live dispatch environment.

3. New Features

Version 7.601

- NA

4. Improved Features and Fixed Issues

Version 7.601

- Licensing
 - Updated Telex License Activation Tool to 1.501, which repairs the Online Activation feature. TLAT 1.500's Online Activation feature did not work, displaying an error "Could not load file or assembly".

5. Known Issues

Version 7.601

- NA

6. Compatibility

Version 7. 601

- Compatible with ADHB-4 Version 3.100.
- Compatible with IP-224 Version 2.400.
- Compatible with Telex License Server 1.300.
- **Not compatible** with the Sentinel/SafeNet/Rainbow keys (USB or Serial). A Flexera Entitlement Certificate (software license) is now required for C-Soft Runtime operation. Please contact Telex Technical Support to acquire Entitlement Certificates.

7. Installation and Upgrade

Version 7.601

- To install C-Soft on Windows 7, Windows 8, and Windows 10:
 - Double click on the C-Soft_vXXXX executable.
 - Follow the steps provided on the screen to install C-Soft.
 - During the C-Soft installation, the user will be prompted to install updated drivers for the ADHB-4. Follow the instructions on the screen to complete ADHB-4 Driver Installation. If up-to-date ADHB-4 Drivers have already been installed, this step can be skipped.

- During the C-Soft installation, the user will be prompted to install Telex License Server, which is required for obtaining and maintaining licenses for C-Soft.
 - The Telex License Server Installer may also install the prerequisite Microsoft Visual C++ 2012 Redistributable package if necessary. If Microsoft Visual C++ 2012 Redistributable is already present, this step can be skipped.
- As necessary, contact Telex Technical Support to acquire license Entitlement Certificates. Consult the C-Soft manual's appendix titled Telex License Activation Tool for more information on licensing requirements, activation processes, and architecture.
- To upgrade C-Soft:
 - Uninstall any previous of C-Soft using the Windows Uninstall Program feature under Control Panel
 - Locate the appropriate version of C-Soft installation package to install C-Soft